





How to configure M3 Mobile Computers for MobileNAV Android application

Configure M3 Mobile Computer

- Launch **EmulScan** application
- Go to **Reading Option** part
- Press **Output Mode**, and select “None(Copy to clipboard)”



- Go to **Data Output**
- Go to **Intent Output** and check “Enabled”



Configure Mobilenav

- Launch **MobileNAV** application
- Log into online or offline
- Click on main menu (MobileNAV icon on the top left)
 - a. Select **Settings**
 - b. Barcode mode: **Device-specific**
 - c. click on **Configure...** button
 - i. Intent action: **com.android.server.scannerservice.broadcast** (same as in EmulScan app in Intent Action)
 - ii. Intent category: (leave empty)
 - iii. Data id: **m3scannerdata**

